

## Re: troubles with bluetooth configuration

**Source:** <http://unix.derkeiler.com/Mailing-Lists/FreeBSD/current/2005-03/0956.html>

---

**From:** Peter Wemm ([peter\\_at\\_wemm.org](mailto:peter_at_wemm.org))

**Date:** 03/31/05

To: [freebsd-current@freebsd.org](mailto:freebsd-current@freebsd.org)

Date: Wed, 30 Mar 2005 15:05:42 -0800

On Wednesday 30 March 2005 09:37 am, Maksim Yevmenkin wrote:

> *Hello,*

>

>> *When I try to initiate my local bt (/etc/rc.bluetooth start ubt0),*

>> *I receive an error message: Can't load ng\_bluetooth.*

>

> *ok, what is the exact error message?*

>

There is a bug in the module declaration in  
sys/netgraph/bluetooth/common/ng\_bluetooth.c

Near 'bluetooth\_mod' there is a string in the structure that says  
"bluetooth" when it should say "ng\_bluetooth".

--- ng\_bluetooth.c 7 Jan 2005 01:45:42 -0000 1.5

+++ ng\_bluetooth.c 30 Mar 2005 23:04:44 -0000

@@ -243,7 +243,7 @@

\*/

```
static moduledata_t bluetooth_mod = {
- "bluetooth",
+ "ng_bluetooth",
    bluetooth_modevent,
    NULL
};
```

The problem is that it is exporting a module called "bluetooth" when the  
scripts and module loader are expecting "ng\_bluetooth".

--

Peter Wemm - [peter@wemm.org](mailto:peter@wemm.org); [peter@FreeBSD.org](mailto:peter@FreeBSD.org); [peter@yahoo-inc.com](mailto:peter@yahoo-inc.com)

"All of this is for nothing if we don't go to the stars" - JMS/B5

---

[freebsd-current@freebsd.org](mailto:freebsd-current@freebsd.org) mailing list

<http://lists.freebsd.org/mailman/listinfo/freebsd-current>

To unsubscribe, send any mail to "[freebsd-current-unsubscribe@freebsd.org](mailto:freebsd-current-unsubscribe@freebsd.org)"