

Re: ESS and AIX 5.2

Source: <http://unix.derkeiler.com/Mailing-Lists/AIX-L/2004-11/0177.html>

From: Bill Verzal (*BVerzal_at_KOMATSUNA.COM*)

Date: 11/16/04

Date: Tue, 16 Nov 2004 07:54:05 -0600
To: aix-l@Princeton.EDU

I'm not using SDD and I don't use VPs.

BV

There's no place like /home

Bill Verzal
Project Leader, Komatsu America

(847) 970-3726 - direct
(847) 970-4184 - fax

"Nguyen, Joseph"
<JNguyen@WM.COM>
Sent by: IBM AIX To
Discussion List aix-l@Princeton.EDU
<aix-l@Princeton.cc
EDU>

Subject

Re: ESS and AIX 5.2

11/15/2004 07:26
PM

Please respond to
IBM AIX
Discussion List
<aix-l@Princeton.
EDU>

It appears that you do not have SDD installed or you have not convert the volume group from hdisk to vpath.
This command requires to umount all filesystems under the VG.

command is hd2vp VGNAME

Joseph

Re: ESS and AIX 5.2

AIX-L: Re: ESS and AIX 5.2

-----Original Message-----

From: IBM AIX Discussion List [mailto:aix-l@Princeton.EDU] On Behalf Of Bill Verzal

Sent: Monday, November 15, 2004 6:51 PM

To: aix-l@Princeton.EDU

Subject: ESS and AIX 5.2

Does anyone know why my ESS drives are showing up multiple times ?

hdisk5 00052267e0fac6b9 datavg active
hdisk6 00052267593124b3 datavg active
hdisk7 0005226759313e29 datavg active
hdisk8 000522675931fa52 RIPBKVG active
hdisk9 00052267e0fac6b9 datavg active
hdisk10 00052267593124b3 datavg active
hdisk11 0005226759313e29 datavg active
hdisk12 000522675931fa52 RIPBKVG active
hdisk13 00052267e0fac6b9 datavg active
hdisk14 00052267593124b3 datavg active
hdisk15 0005226759313e29 datavg active
hdisk16 000522675931fa52 RIPBKVG active
hdisk17 00052267e0fac6b9 datavg active
hdisk18 00052267593124b3 datavg active
hdisk19 0005226759313e29 datavg active
hdisk20 000522675931fa52 RIPBKVG active
hdisk21 00052267e0fac6b9 datavg active
hdisk22 00052267593124b3 datavg active
hdisk23 0005226759313e29 datavg active
hdisk24 000522675931fa52 RIPBKVG active
hdisk25 00052267e0fac6b9 datavg active
hdisk26 00052267593124b3 datavg active
hdisk27 0005226759313e29 datavg active
hdisk28 000522675931fa52 RIPBKVG active
hdisk29 00052267e0fac6b9 datavg active
hdisk30 00052267593124b3 datavg active
hdisk31 0005226759313e29 datavg active

These are in fact all the same physical drives. But they're repeated.

BV

There's no place like /home

Bill Verzal
Project Leader, Komatsu America

(847) 970-3726 - direct
(847) 970-4184 - fax