

Re: HEADS UP: LC_CTYPE format changed

Source: <http://unix.derkeiler.com/Mailing-Lists/FreeBSD/current/2005-03/0099.html>

From: Tai-hwa Liang (avatar_at_mmlab.cse.yzu.edu.tw)

Date: 03/03/05

Date: Thu, 3 Mar 2005 21:27:33 +0800 (CST)

To: Ruslan Ermilov <ru@freebsd.org>

On Thu, 3 Mar 2005, Ruslan Ermilov wrote:

> On Thu, Mar 03, 2005 at 10:28:41AM +0800, Tai-hwa Liang wrote:

>> On Sun, 27 Feb 2005, Ruslan Ermilov wrote:

>>> I've just committed changes that modify the format of LC_CTYPE

>>> files. Next time when you buildworld/installworld, please do

>>> it without `-DNO_CLEAN`, or at least remove the contents of

>>> `/usr/obj/usr/src/share/mklocale/`.

>>

>> Not sure if I missed something. But after making a clean buildworld

>> & installworld, perl always pops with following warnings:

>>

>> perl: warning: Setting locale failed.

>> perl: warning: Please check that your locale settings:

>> `LC_ALL = (unset)`,

>> `LC_CTYPE = "zh_TW.Big5"`,

>> `LANG = "zh_TW.Big5"`

>> are supported and installed on your system.

>> perl: warning: Falling back to the standard locale ("C").

>>

>> Re-building perl5.8 from ports doesn't seem to help.

>>

> I don't know what's your problem (make sure your ``which perl``

> isn't linked to `libc.so.5`), but it definitely works here:

>

> : `$ hostname`

> : `sledge.freebsd.org`

> : `$ uname -mir`

> : `6.0-CURRENT amd64 SLEDGE`

> : `$ grep __FreeBSD_version /usr/include/osreldate.h`

> : `#undef __FreeBSD_version`

> : `#define __FreeBSD_version 600019`

> : `$ env LC_ALL="unknown" perl -e exit`

> : perl: warning: Setting locale failed.

> : perl: warning: Please check that your locale settings:

> : `LC_ALL = "unknown"`,

> : `LANG = (unset)`

> : are supported and installed on your system.

freebsd-current: Re: HEADS UP: LC_CTYPE format changed

```
> : perl: warning: Falling back to the standard locale ("C").
> : $ env LC_ALL="zh_TW.Big5" perl -e exit
> : $
>
> (Also check /etc/libmap.conf.)

> uname -mir
6.0-CURRENT i386 f22-r40
> grep __FreeBSD_version /usr/include/osreldate.h
#undef __FreeBSD_version
#define __FreeBSD_version 600019
> ls -la /etc/libmap.conf
ls: /etc/libmap.conf: No such file or directory
> ldd `which perl`
/usr/bin/perl:
  libperl.so => /usr/local/lib/perl5/5.8.6/mach/CORE/libperl.so (0x28075000)
  libm.so.3 => /lib/libm.so.3 (0x28176000)
  libcrypt.so.2 => /lib/libcrypt.so.2 (0x2818a000)
  libutil.so.4 => /lib/libutil.so.4 (0x281a2000)
  libc.so.6 => /lib/libc.so.6 (0x281ae000)
> env LC_ALL="unknown" perl -e exit
perl: warning: Setting locale failed.
perl: warning: Please check that your locale settings:
  LC_ALL = "unknown",
  LC_CTYPE = "zh_TW.Big5",
  LANG = "zh_TW.Big5"
  are supported and installed on your system.
perl: warning: Falling back to the standard locale ("C").
> env LC_ALL="zh_TW.Big5" perl -e exit
perl: warning: Setting locale failed.
perl: warning: Please check that your locale settings:
  LC_ALL = "zh_TW.Big5",
  LC_CTYPE = "zh_TW.Big5",
  LANG = "zh_TW.Big5"
  are supported and installed on your system.
perl: warning: Falling back to the standard locale ("C").
> unsetenv LC_CTYPE && env LC_ALL="zh_TW.Big5" perl -e exit
perl: warning: Setting locale failed.
perl: warning: Please check that your locale settings:
  LC_ALL = "zh_TW.Big5",
  LANG = "zh_TW.Big5"
  are supported and installed on your system.
perl: warning: Falling back to the standard locale ("C").
> unsetenv LANG && env LC_ALL="zh_TW.Big5" perl -e exit
perl: warning: Setting locale failed.
perl: warning: Please check that your locale settings:
  LC_ALL = "zh_TW.Big5",
  LANG = (unset)
  are supported and installed on your system.
perl: warning: Falling back to the standard locale ("C").
> env LC_ALL="" perl -e exit
```

freebsd-current: Re: HEADS UP: LC_CTYPE format changed

>

freebsd-current@freebsd.org mailing list

<http://lists.freebsd.org/mailman/listinfo/freebsd-current>

To unsubscribe, send any mail to "freebsd-current-unsubscribe@freebsd.org"