

import raw EMC device to zone

Source: <http://unix.derkeiler.com/Mailing-Lists/SunManagers/2008-03/msg00040.html>

- *From:* "Ronelle van Niekerk" <Ronelle.vanNiekerk@xxxxxxxxxxxxxxxxxxxxx>
 - *Date:* Mon, 10 Mar 2008 15:26:57 +0200
-

Guys,

I am new to this SUN containers thing and am trying to learn without the benefit of someone who actually knows what they're doing.

I have some EMC "disks" on the global zone and would like to import them into the two zones on that domain, but I am struggling.

I am following an example given to me by my SUN partners as follows:

```
global# zonecfg -z zone1
add device
set match=/dev/rdisk/c1t0d0s6
end
add device
set match=/dev/dsk/c1t0d0s6
end
```

I reboot the zone and zlogin to it, but nothing.

The problem is that I don't know which devices to use.

/dev/rdisk/emcpower0 and /dev/dsk/emcpower0 don't seem to work, neither does emcpower0a.

import raw EMC device to zone

Which devices should I be using?

And am I doing this right?

Running Solaris 10 on all globals and zones.

A format gives me these devices:

2. c1t5006016939A03A0Bd0 <DGC-RAID5-0324 cyl 61438 alt 2 hd 256 sec 20>

/pci@3,700000/SUNW,emlxs@0/fp@0,0/ssd@w5006016939a03a0b,0

3. c1t5006016039A03A0Bd0 <DGC-RAID5-0324 cyl 61438 alt 2 hd 256 sec 20>

/pci@3,700000/SUNW,emlxs@0/fp@0,0/ssd@w5006016039a03a0b,0

4. c1t5006016039A03A0Bd1 <DGC-RAID5-0324 cyl 51198 alt 2 hd 256 sec 16>

/pci@3,700000/SUNW,emlxs@0/fp@0,0/ssd@w5006016039a03a0b,1

5. c1t5006016939A03A0Bd1 <DGC-RAID5-0324 cyl 51198 alt 2 hd 256 sec 16>

/pci@3,700000/SUNW,emlxs@0/fp@0,0/ssd@w5006016939a03a0b,1

6. c1t5006016039A03A0Bd2 <DGC-RAID5-0324 cyl 51198 alt 2 hd 256 sec 16>

/pci@3,700000/SUNW,emlxs@0/fp@0,0/ssd@w5006016039a03a0b,2

7. c1t5006016939A03A0Bd2 <DGC-RAID5-0324 cyl 51198 alt 2 hd 256 sec 16>

/pci@3,700000/SUNW,emlxs@0/fp@0,0/ssd@w5006016939a03a0b,2

8. c1t5006016039A03A0Bd3 <DGC-RAID5-0324 cyl 61438 alt 2 hd 256 sec 20>

/pci@3,700000/SUNW,emlxs@0/fp@0,0/ssd@w5006016039a03a0b,3

9. c1t5006016939A03A0Bd3 <DGC-RAID5-0324 cyl 61438 alt 2 hd 256 sec 20>

/pci@3,700000/SUNW,emlxs@0/fp@0,0/ssd@w5006016939a03a0b,3

10. emcpower0a <DGC-RAID5-0324 cyl 61438 alt 2 hd 256 sec 20>

import raw EMC device to zone

import raw EMC device to zone

/pseudo/emcp@0

11. emcpower1a <DGC-RAID5-0324 cyl 51198 alt 2 hd 256 sec 16>

/pseudo/emcp@1

12. emcpower2a <DGC-RAID5-0324 cyl 51198 alt 2 hd 256 sec 16>

/pseudo/emcp@2

13. emcpower3a <DGC-RAID5-0324 cyl 61438 alt 2 hd 256 sec 20>

/pseudo/emcp@3

-Ronelle van Niekerk

sunmanagers mailing list

sunmanagers@xxxxxxxxxxxxxxxxx

<http://www.sunmanagers.org/mailman/listinfo/sunmanagers>